

# **BIXOLON SAMSUNG USB & LPT Device Driver Installation Manual**

## **Printer Model**

**SRP -350/SRP-370  
SRP-372/SRP-270  
SRP-275/SRP-280  
SRP-500/SRP-350F  
SRP-350plus**

---

## Contents

|  |          |
|--|----------|
| <b>1. Foreword ...</b>                         | <b>2</b> |
| <b>2. Operating Environment ...</b>            | <b>2</b> |
| <b>3. Installing the USB Device Driver ...</b> | <b>3</b> |
| 3.1 Windows 98/ME ...                          | 3        |
| 3.2 Windows 2000 ...                           | 10       |
| 3.2 Windows XP/2003 ...                        | 14       |

---

## 1. Foreword

---

When interface of printer is USB type or “Add new hardware wizard” is pop-up from LPT PnP(plug-and-play), this manual explains how to install the Windows Driver.

## 2. Operating Environment

---


- Microsoft Windows 98 Gold
- Microsoft Windows 98 Second Edition
- Microsoft Windows Millennium Edition
- Microsoft Windows 2000
- Microsoft Windows XP
- Microsoft Windows 2003 Server
- Microsoft Windows Embedded For Point Of Service

### 3. Installing the USB Device Driver


---

#### 3.1 Windows 98/ME


- (1) Double click the Installer file.
- (2) Click the "Next" Button.



(3) Click the “Install” Button.




- (4) Select the “USB” interface(port) type.



- (5) After restarting the system, turn-on the printer.



- (6) When “Add new hardware wizard” pop-ups to install the “USB print support” driver, then click the “Next” button.




(7) Please click “Next” button continuously.






(8) When “USB print support” driver has installed, your system will restart automatically.






- (9) After System's rebooting, printer driver has been installed automatically.




- (10) Appoint the place when there is an error while software installing.




※appoint the place : "C:\WINDOWS\model name(SRP-350, 350plus, SRP-280, etc)\usb"

- (11) USB Port has been set-up in Driver properties.




### 3.2 Windows 2000


- (1) Double click the Installer file.
- (2) Click the "Next" Button.



(3) Click the “Install” Button.



(4) Select the “USB” interface(port) type.






※When You see the Warning Pop-up like above picture, please click the Yes button. It doesn't take any bad affect to the OS as well as no problem to use the printer and driver.


(5) Please turn-on the printer.



(6) Driver has been installed automatically.




(7) USB Port has been set-up in Driver properties.




### 3.3 Windows XP/2003 Server

- (1) Double click the Installer file.
- (2) Click the "Next" Button.




(3) Click the “Install” Button.






- (4) Select the “USB” interface(port) type.



※When You see the Warning Pop-up like above picture, please click the Yes button. It doesn't take any bad affect to the OS as well as no problem to use the printer and driver.


- (5) Please turn on the printer as the message below.





- (6) When “Add new hardware wizard” pop-ups to install the “USB print support” driver, then click the “Next” button.




(7) Click the next button continuously.








※When You see the Warning Pop-up like above picture, please click the next button. It doesn't take any bad affect to the OS as well as no problem to use the printer and driver.



(8) Click the “finish” button.



(9) USB Port has been set-up in Driver properties.

